


# PontiVoce™ Connects You to the World



## Using the Pontivoce Software, v3.0

PontiVoce software offers a means for shared use and controlled access to a PC running Skype—for you and for selected friends and family. The control software is a server module installed in your PC as the master control of your Skype application. It enables selected users to access Skype to make calls.

## Call from Your Mobile or Any Phone

The Pontivoce server software can be configured to allow any number of phones to call in and be allowed to place calls. Calls must be recognized by CallerID as reported by Skype (requires Skypeln). When a recognized phone calls in, the Pontivoce software answers the Skype call and plays a tone. You may connect conference calls as allowed by the resources of your PC, up to 10 total parties on a call.

There are two modes of operation depending on what may be best for your calling plan. The call back mode calls you back and the other dialed parties. In the pass through mode you do not hang up, but stay on the line while the other call or calls are placed.


After the tone, enter the number or numbers to be called. Separate each number entered with a '\*'.' Called numbers can be Skype 2-digit speed dial numbers or any international phone number, entered starting with the country code.

The dial string must be terminated with '#' when in the call through mode. If the call back mode is used you may simply hangup at the end of the request. PontiVoce will call all parties simultaneously. A message is played to let the answering party know others will join. In the call through mode you will hear a tone indicating that you are joining the call that has been setup.

Called parties may leave the conference at any time. As the originator when you end the call all parties are disconnected.

### **PontiVoce Setup for Use as a Mobile Gateway**

1. Click on the Telephone Authorization tab. Enter the phone numbers of allowed callers (e.g., your mobile phone number, etc.) Enter numbers as Skype reports: +, country code, number.
2. When you call on your SkypeIn line from an authorized number (and Skype reports the CallerID), PontiVoce will answer the call and play a tone sequence.
3. Enter the number or numbers to be called. PontiVoce will complete the call based on the configuration of call back or call through. For conference calls separate numbers with a "\*".' At the end of the sequence press "#" or you can hang-up if configured in call back mode.
4. To call any of your Skype contacts enter the speed dial number, as assigned using the Skype option. (Right click on name to set and then restart PontiVoce.) This can also be used to dial phone numbers.



5. To call a regular phone you must have SkypeOut. Dial the number starting with the country code. You can mix Skype contacts with regular phone calls, just as you can at your PC.

### Enabling Remote Access by a Skype User

PontiVoce allows named callers to have limited control over your Skype application to set up a telephone (SkypeOut) call using your PC as a host (server) for the call. Calls can be restricted to a country code as specified or you may allow callers to reach any phone number.

### PontiVoce Server Setup

When the PontiVoce server launches it captures all Skype names.

1. Click on the Permit Client Callers tab. Select by checking the box for each Skype user that you wish to allow to use the PontiVoce Server. As you click a name, a Skype IM is sent to let the person know that you have allowed them to use the PontiVoce Server.
2. You may enter names not on your buddy list in the window below the buddy list. Each name must be separated by a space. The best practice is to add a space at the end of the name, so that names added by clicking will be seen as valid.



try different servers to make a call. *You must be authorized to make a call request from the PontiVoce Client software.*



The free PontiVoce Client software sends a request for a call to the PC running the Server software. Both PCs must be logged on to Skype. To make a call simply enter the number to be called and press the Call button. The status of the request and call is indicated below the window of the dialed number. Where the server may not be in an active state a second request may be required. The Server PC responds by placing a call to the requested phone number and calls back the Client (all on Skype) to establish the requested call.

### Other Uses

The PontiVoce server enables a flexible call forwarding for Skype users. By selectively granting access to the PontiVoce server, only specific callers will be able to forward to the Skype user's cell or other phone. There is no need to be tied to the PC to benefit from free calling and accessibility to the callers desired. PontiVoce software can be used to simply call a user's home phone or mobile, so there is no need to be able to hear PC speakers to receive a Skype call.

For reference the Skype name can be found at the top of the Skype application.

